



Supramatic Bluetooth App




In order to operate your SupraMatic via the Bluetooth function you will first need to download the app from the App/Play store, the name of the app is 'BlueSecur'.

In order to operate your SupraMatic via the Bluetooth function you will first need to download the app from the App/Play store, the name of the app is 'BlueSecur'.	
Once downloaded open the app and when prompted allow permissions for access to the 'Camera', Bluetooth® & Location	
Turn on the Bluetooth® on the operator, the symbol will begin to flash red slowly until it has made the connection, 5 minutes has passed or it is turned off.	
At the top of the app you have a title Devices followed by +, this symbol will allow you to connect a new device to the app, when you press the + sign your camera will open looking for a QR code, this is found both on the motor head & the Blue card supplied with the unit	
Line up the QR code until the camera 'recognises' it you will then be told the unit is syncing and can take up to 20 second.	
Once synched you need to name the device, it will then appear under Devices on the screen with the impulse function shown.	


Supramatic Bluetooth App




At this point you are the administrator and the device is registered to your phone, for back up you may want to create a login in case you change your device or have an issue. At the top of the screen you have a menu option ...




Select login and follow the on screen directions and register your account.



The device comes with one electronic key to obtain more select 'Set of keys' from the menu option









At the top you can see the number of keys you have available and purchase additional keys for distribution



Supramatic Bluetooth App




You are now ready to create and distribute keys for your devices, these can be temporary one time use keys, a limited time key, an additional administrator key or a user key. To begin first click on the yellow cog next to the device name.	
This opens up the administrator page where you can see your issued keys, device settings and the option to delete the device from the app. To create an additional key click on the plus symbol, this will allow you to choose the key type as a user key or one-time use key, for this example we are making a user key.	
To enable you to keep track of the key you must name it and decide on the validity of the key, either a permanent key, a onetime use or a key valid for a set time period.	
Once you have named it you can choose to share it now or share it later. If shared later it will appear in your list as 'Not distributed' until you choose to do so you click on it you have the option to rename it or distribute it.	
Whilst there are two methods of distribution we find the email option to work better than the SMS option, your recipient will receive a message with a link to the website.	
Once you have entered your method you are then prompted by your phone / tablet to distribute the key, whilst this seems double the work the first input is for our system in Germany which tracks the device to ensure it can only be downloaded by the intended recipient contact method. Again we recommend the email option.	


Supramatic Bluetooth App



Once distributed it will show the status in your listing identifying distributed keys and non-distributed keys.




Your recipient will receive the link to our key page



If they have the app they click on 'Open in the app' if they don't have the app they can be directed to the relevant store to download this for free.







Once they click on the 'Open in the App' link they will receive the notification shown if you have shared with a password or distributed later



Supramatic Bluetooth App







At this point our system generates a second email with a onetime use code	
Once received input the code (it is valid for 10 mins) and click 'Import key' the app will then begin importing the key, they must be in range of the Bluetooth® device	
The second unit will now show the device	
If you reach a stage where you have blocked the unit and are unable to reclaim your purchased key, you need to perform a full reset on both the main phone and the Bluetooth unit, this is done as follows:	

Resetting your Phone:	
To begin first click on the yellow cog next to the device name.	

Supramatic Bluetooth App



Select the three white dots / trash can in the top right hand corner of the device administration page and select 'Delete' from the options	
You will receive the following prompt to ensure this is an action you wish to perform	
Once you select 'Yes' you will be advised to reset the Bluetooth device	
The device will now disappear from the list of available devices on your app, any keys purchased will reappear in your 'key bank'	

Resetting the Operator:	
Press and hold the 'PRG' button until the display shows '00'	
Using the up arrow change the display to '19'	
Press the 'PRG' button and the display will then show '00' flashing slowly	
Use the up arrow until the display then shows '02' flashing slowly	
Press and hold the 'PRG' button until the '19' reappears in the display	
Using the down arrow change the display back down to '00' before pressing the 'PRG' button to exit	
Turn on the Bluetooth® on the operator, the symbol will begin to flash red slowly until it has made the connection, 5 minutes has passed or it is turned off.	
Now you are ready to begin again coding the Bluetooth to your phone.	